| Title: | Number: | Revision | Date |
|-------------|---------------|--------------------|----------|
| File | | Number: | Issued: |
| Maintenance | WI-100-UG-007 | 1 | 05-01-98 |
| | Prepared By: | Approved By: | Page: |
| | Jennifer Rey | Bob Oborsky | 1 of 59 |
| | | | |

LIS user guides and revision are approved by AML-100 Division Manager and are controlled on the FAALC Intranet. If printed or copied, they become uncontrolled and may be used only if the user assures they contain the latest revisions.

LIS

FILE MAINTENANCE



USER GUIDE

MAY 1998

PREFACE

This User Guide is intended for the use of Federal Aviation Administration (FAA) personnel who have authorized access to the Logistics and Inventory System (LIS).

TABLE OF CONTENT

| 1.0 | OVERVIEW | 1 |
|-----|-----------------------------------|-----|
| 2.0 | LOGGING ON THE LIS | . 8 |
| 3.0 | FILE MAINTENANCE MAIN MENU | 13 |
| 4.0 | SPECIAL FEATURES AND APPLICATIONS | 52 |

1.0 OVERVIEW

1.1 GENERAL DESCRIPTION

File Maintenance is a function in the Inventory Management Subsystem of the Logistics And Inventory System. It is an online process featuring data entry screens designed to provide users with the ability to change certain non-accountable data fields in the Master Inventory Record and subsidiary item support files. These data fields are used to accommodate key elements of data required to manage items of supply within the centralized inventory and distribution system operated by the Federal Aviation Administration (FAA) Logistics Center. The integrity of these data elements is essential and restrictions apply to certain data elements. File Maintenance is an integral function for insuring timely online update of these fields when required.

1.2 BENEFITS

This menu driven, user friendly function, will guide the user to specific work areas. The FAST - PATH option provides a window on the screen to allow for efficient movement between screens without returning to the Main Menu.

FIELD DEFINITIONS are available to the user on all fields requiring data entry.

A TRACKING NUMBER is assigned to every transaction. It is used for tracking and identification.

The number is mechanically assigned at the time the transaction processes or attempts to process. The TRANSACTION NUMBER will be displayed in the FAST - PATH window.

Access to functions is controlled by security level. Each user is assigned to a appropriate security level to perform required tasks. Unauthorized users will be restricted from accessing certain function.

Electronic Exception Notices are mechanically routed to the appropriate Item Manager. Correction and reprocessing is accomplished via Queue Management. This process replaces the hard copy exception notices in the National Supply System (NS) which is not adequately controlled.

All Issues, Receipts, Adjustment and File Maintenance transactions processed in the LIS will build transaction history records. The LIS provides the user the ability to inquire and review up to five years of transaction history online, with an option to print reports for specified periods.

1.3 SECURITY LEVELS FOR FILE MAINTENANCE

The File Maintenance function requires security levels to maintain the integrity of the process.

Unauthorized users attempting this function will receive an error message, INVALID OPTION FOR YOUR SECURITY LEVEL, which will be displayed in the upper left corner of the screen.

Valid security levels are as follows:

LEVEL 2 - AML-600 CLERKS

Inquiry capability into all LIS database and tables with limited update (add, modify, delete) capability on the Procurement Database. This security level cannot approve a Purchase Request. This security level can enter Issues, File Maintenance (except Warehouse Location File Maintenance), and Due Ins. This security level does not have access to Queue Management.

LEVEL 3 - AML-600 ITEM MANAGERS and EQUIPMENT SPECIALISTS. Inquiry capability into all LIS databases and tables. This security level has access with update capability to Issues, Adjustments, File Maintenance (except Warehouse Location File Maintenance), Due Ins, Procurement and Queue Management. This security level does not have access to Receipts. This security level allows for approval of Purchase Requests subject to approval authority.

LEVEL 4 - AML-600 MANAGEMENT

Inquiry Capability into all LIS databases and tables. This security level has access with update capability to Issues, Adjustments, File Maintenance (except Warehouse Location File Maintenance), Due Ins, Procurement and Queue Management and limited update capability into Procurement Tables. This security level does not have access to Receipts. This security level allows for approval of Purchase Requests subjects to approval authority.

LEVEL 5 - AML-600 CONTROL GROUP (AML-610)

Inquiry capability into all LIS databases and tables with full update capability into all Procurement databases and tables. This security level has access with update capability to Issues, Adjustments, file Maintenance (except Warehouse Location File Maintenance), Due Ins, Procurement and Queue Management. This security level does not have access to Receipts. This security level allows for approval of Purchase Requests subject to approval authority.

LEVEL 6 - AML-340 RECORD AUDIT AND UPDATE SUPERVISOR, SUPPLY CLERKS AND SUPPLY TECHNICIANS.

Inquiry capability into all LIS databases and tables. This security level has full update capability for Receipts and access to Queue Management for Receipts. This security level can enter and process Issues, enter Adjustments, and has full update capability to Shipping Information.

This security level does not have access to Procurement or Due Ins. This security level has access to File Maintenance for maintaining Warehouse Location.

LEVEL A - AML-610 INVENTORY MONITOR

Inquiry capability into all LIS databases and tables. This security level has access to Queue Management for processing Cycle Inventory Thaws (03T) and Adjustments (10, 11,25 and 26). This security level has access to File Maintenance for Maintaining Pre-Inventory Date and Current Status Code 4.

LEVEL C - AML-340 WAREHOUSE LOCATION

Inquiry capability into all LIS Databases and Tables. This security level has limited access to File Maintenance for maintaining Warehouse Locations.

LEVEL F - AML-370 FREIGHT CLASSIFICATION SPECIALIST Inquiry Capability into all LIS Databases and Tables. This security level has limited access to File Maintenance for maintaining Transportation Codes and selected Special Handling Codes. This security level has access to Queue Management for reviewing and processing Special Handling Codes.

LEVEL G - AML-500 QUALITY ASSURANCE DIVISION

Inquiry capability into all LIS Databases and Tables. This security level has limited access to File Maintenance for maintaining Special Handling Codes.

LEVEL H - AmI-300 SYSTEMS GROUP

This security level has access to Queue Management for processing File Maintenance Exception.

LEVEL J - AML-310 ACCEPT AND DISTRIBUTION. AML-370 TRANSPORTATION SERVICE BRANCH

Inquiry capability into all LIS databases and tables. This security level has limited access to File Maintenance for Maintaining selected Special Handling Codes.

LEVEL K - AML-340 INVENTORY CONTROL GROUP Inquiry capability into all LIS databases and tables. This security level has access to File maintenance for maintaining Warehouse Location and a selected Transportation Code

1.4 STANDARD NOTATION FOR INPUT FROM THE KEYBOARD

Throughout the LIS USER GUIDE, the following conventions will be used consistently to indicate user keyboard entry EXAMPLE:

| When the user sees | It represents | Example |
|-------------------------------|--|--|
| [] (square brackets) | a specified key that should be pressed. | [ENTER] |
| <> (greater than & less than) | the data to be input | <99> <01> |
| ALL CAPITAL LETTERS | a data or field name | TRANSACTION CODE CONTROL NUMBER |
| BOLD CAPS | information from the actual screen | <99> - TO CANCEL OR RE- TURN TO LIS MAIN MENU |
| Press | instructions to depress a key or Keys | Press [ENTER] |
| Input | instructions to type the specified input | input option NUMBER <2> |
| NOTE: | important information | NOTE: Set printer for 132 column output |
| [keyname]-[keyname] | combinations of keys to press together | Hold the first key down, press the SECOND |

2.0 LOGGING ON THE LIS

```
FFFFFFFF AAAAA
                          AAAAA
                                   NNN
                                             NNN
                                                  EEEEEEEE
    FFFFFFFF AAAAAAA
                         AAAAAAA
                                   NNNN
                                            NNN
                                                 EEEEEEEE TTTTTTTTTT
              AAA AAA
                        AAA
                              AAA NNNNN
                                           NNN
   FFF
                                                 EEE
                                                              TTT
             AAAAAAA
                       AAAAAAA
                                 NNN
                                       NN
                                           NNN
                                                EEEEEEEE
                                                             TTT
                       AAAAAAA
  FFFFFFFF AAAAAAA
                                 NNN
                                       NN NNN
                                               EEEEEEEE
                                                             TTT
                                NNN
 FFF
            AAA
                AAA
                      AAA AAA
                                                            TTT
                                        NNNNN
                                               REE
FFF
           AAA AAA
                     AAA
                           AAA
                                NNN
                                              EEEEEEEE
                                                           TTT
                                        NNNN
FFF
           AAA AAA AAA
                               NNN
                                         NNN EEEEEEEE
                                                           TTT
                                                                PX 3.5
                UNAUTHORIZED ACCESS IS CONSIDERED A CRIMINAL ACT.
      WARNING:
                 SECTIONS 641 AND 1030 OF TITLE 18 USC.
                 LEASE ENTER REQUESTED ACCESS INFORMATION
                                     P210
    LOGON-ID :LGACXXX
                        HOST:
                                            DATE :10/16/95
   * PASSWORD : * * * * * * * * TERMINAL - ID : LG03LU64 TIME : 07:34:42
   * NEW PASSWORD:
                        TRANSFER:
                                               MODEL :3292-2A
                                                HELP : (405) 954-3000
*** PRODUCTION TPX ON SYSTEM P210 ***
FOR HELP DESK DIRECTORY SELECT "HELP DESK" APPLICATION FROM YOUR MENU
PF1 = HELP
             PF3 = LOGOFF
```

FIGURE 1

Input USER ID CODE at the USER ID field. [TAB] to PASSWORD, and input the assigned PASSWORD. Press **[ENTER]**. Logon to the LIS is complete.

2.1 LIS MAIN SYSTEM MENU

```
10/03/90
                         FAA LOGISTICS AND INVENTORY SYSTEM
                                                                         T.TS010
                             ** MAIN SYSTEM MENU **
        LIS STAFF HOT-LINE NUMBERS: FTS: 747-3447
                                                     COMM: 405 680-3447
 1-PROJECT MATERIEL PRODUCTION SYSTEM
                                            2-NAME/ADDRESS RECORD CHANGE
 3-UTILIZATION SCREENING & DISPOSITION
                                            4-ENGINEERING DATABASE
 5-CATALOGING
                                            6-CUSTOMER SERVICE EVALUATION
 7-PROCUREMENT SYSTEM
                                            8-MANAGEMENT INFORMATION SYSTEM
 9-ON-LINE REQUISITIONING
                                           10-MAIL/CONNECT
11-INVENTORY MANAGEMENT
                                  99 - LOGOFF
                                ENTER OPTION :11
```

FIGURE 2

After logging onto the Logistics and Inventory System (LIS), the user will reach the LIS MAIN SYSTEM MENU - LIS010. Here the user decides which LIS application to access.

Each **LIS MAIN MENU** is tailored to fit the application needs of the user; therefore, the number of the option corresponding to the application will differ from user to user, In the above example, OPTION < 11 > is for INVENTORY MANAGEMENT. To access File Maintenance, input < 11 > at the enter OPTION. Press **[ENTER]** and the **LIS INVENTORY MANAGEMENT MAIN MENU** - INVO01, (Pg. 10) will be displayed.

2.2 LIS INVENTORY MANAGEMENT MAIN MENU

| 10/30/90 LIS / INVENTORY MANAGEMENT ** MAIN MENU ** | INV001 |
|--|--------|
| 1 - ISSUES MENU 2 - RECEIPTS MENU 3 - ADJUSTMENTS MENU 4 - FILE MAINTENANCE MENU 5 - QUEUE MANAGEMENT MENU 6 - INQUIRIES MENU 7 - ESTABLISH ADVANCE DUE-IN/DUE-IN MENU 8 - AUTOMATED PROCUREMENT MENU 9 - WAREHOUSE LOCATOR LABEL 99 - EXIT TO LIS MAIN MENU | |
| ENTER OPTION : _4_ TRANS-CD/MOD : NSN/SUFFIX : _ VOUCHER-NBR : CONTROL-NBR : | |

FIGURE 3

From this menu, the user can access the applicable functions within authorized security level by selecting the OPTION NUMBER, or by using **FAST - PATH**. See **LIS INVENTORY MANAGEMENT MAIN MENU** - **INV001**, (Pg. 11), **USING FAST - PATH**. To access the File Maintenance function, the user will input OPTION < 4 >. Press **[ENTER]** and the **FILE MAINTENANCE MAIN MENU** - **FIL010**, (Pg. 13), will be displayed.

2.3 $\,$ LIS INVENTORY MANAGEMENT MAIN MENU THE FAST - PATH FEATURE

```
10/30/90
                                                                 TNV001
                        LIS / INVENTORY MANAGEMENT
                                MAIN MENU
                 1 - ISSUES MENU
                 2 - RECEIPTS MENU
                 3 - ADJUSTMENTS MENU
                 4 - FILE MAINTENANCE MENU
                 5 - OUEUE MANAGEMENT MENU
                 6 - INQUIRIES MENU
                 7 - ESTABLISH ADVANCE DUE-IN/DUE-IN MENU
                 8 - AUTOMATED PROCUREMENT MENU
                 9 - WAREHOUSE LOCATOR LABEL
                99 - EXIT TO LIS MAIN MENU
                             ENTER OPTION:
                            TRANS-CD/MOD: 04 B
                             NSN/SUFFIX : 2840 00 307 8960
                             VOUCHER-NBR: 92441230
                             CONTROL-NBR:
```

FIGURE 4

The user can also select to use the FAST - PATH feature. The FAST - PATH feature is located in the area below the enter OPTION field on this menu. This feature is designed to give direct access to other processing screens or functions without having to exit to a selection menu.

NOTE: OPTION NUMBER is not required when using the FAST - PATH feature. The TRANSACTION CODE dictates the function to access.

To access process screens within the Field Maintenance function, the user is required to input the TRANSACTION CODE, MODIFIER, NSN and VOUCHER NUMBER or CONTROL NUMBER. Press [ENTER].

NOTE: The cursor will move to the next data field when all positions are input. When the cursor does not advance to the next data field, the user can move between data fields by pressing [TAB].

NOTE: FIELD DEFINITION is a feature of this function. This feature is useful if the user is unfamiliar with a data field. The user will input a question mark (?) in the unfamiliar field. Press **[ENTER]** again and the screen will return to continue processing. See **FIELD DEFINITION EXAMPLE** - **FIL010**, (Pg. 54)

3.0 LIS FILE MAINTENANCE MAIN MENU

| 11/03/90 | LIS/FILE MAINTENANCE | FIL010 |
|-------------------------------|--------------------------------------|-----------------------|
| | ** MAIN MENU ** | |
| 1 - CANCEL DUE OUT | (04B) 11 - MODIFY I | N SHOPS (03N) |
| 2 - RELEASE DUE OU | (06Y) 12 - MODIFY B | ORROWED (03P) |
| 3 - MODIFY DUE OUT | (03B) 13 - MODIFY L | OANED (03M) |
| 4 - DELETE MASTER INVENTORY | (01T) 14 - MODIFY I | NVENTORY DEMAND (03J) |
| 5 - MODIFY MASTER INVENTORY | (03T) 15 - REQUEST | STATUS CARD (09R) |
| 6 - MODIFY MANAGEMENT FIELDS | S (03L) 16 - MASS ITE | M MGR. CHANGE |
| 7 - MODIFY WAREHOUSE LOCATION | ONS (03T/03Q) | |
| 8 - MODIFY ADVANCE DUE IN | (03A) | |
| 9 - MODIFY DUE IN | (03D) 99 - EXIT TO | INVENTORY MANAGEMENT |
| 10 - MODIFY DUE IN FACILITY | (03F) MAIN MEN | U |
| | ENTER OPTION: | |
| OPTION 1-14 1-3 8-13 | NSN: VOUCHER-NBR: CONTROL-NBR: | |

FIGURE 5

The **LIS FILE MAINTENANCE MAIN MENU - FIL010** is shown in Figure 5, displays the OPTIONs available within the File Maintenance function.

A Master Inventory Record or Subsidiary File can be updated using the Transaction listed above.

Input the appropriate OPTION NUMBER in the enter OPTION field. The NSN, VOUCHER NUMBER or CONTROL NUMBER is required for certain options.

<u>NOTE</u>: Invalid data will result in an error message. See **ERROR MESSAGE EXAMPLE** - FIL010, (Pg. 52).

OPTION <99> **EXIT TO INVENTORY MANAGEMENT MAIN MENU**. If the user chooses to exit the current screen, this option will disregard the input data and return the user to the **LIS INVENTORY MANAGEMENT MAIN MENU** - INV001, (Pg. 10).

3.1 04B CANCEL DUE OUT - FIL015

| 02/08/90 | LIS / FILE MAINTENANCE ** 04B CANCEL DUE OUT ** | FIL015 |
|---|---|--------------|
| NSN : 2840 00 307 8960 | _ ISSUE VOUCHER : 92441230 | PRI: 5_ |
| TRANS-CD/TC-MOD : 80 | B D/O QUANTITY : 2 | _ |
| SELECT ONE ACTION FROM | LIST BELOW: | |
| _ PARTIAL BACK ORDER CA _ BACK ORDER CANCELLED | O. ACTION REQUESTED OR AUTHORIZED BY ANCELLED - SHIP-QTY CHANGED TO REQUISITION SUBMITTED FOR DIRECT S - REQUISITION SUBMITTED TO GAS/DOD F | SHIP |
| _ BACK ORDER CANCELLED | - SUBSUITUTE NSN : | _ |
| | 1 - SELECT FAST PATH EXITS 9 - EXIT TO FIELD/FILE MAINTENA | |
| ENTER OPTION : | 99 - EXIT TO INVENTORY MANAGEMEN | NT MAIN MENU |

FIGURE 6

OPTION <1> of the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13) is to manually cancel all or part of a Back Order on the Due Out File, TRANSACTION CODE 04B. Access is by security level 3, 4 or 5.

The NSN, ISSUE VOUCHER NUMBER, TRANSACTION CODE and MODIFIER, Due Out QUANTITY (D/O QUANTITY), and PRIORITY CODE (PRI) are automatically displayed with data from the Due Out File.

The cursor will be located in the first ACTION CODE field. Tab the cursor to the desired action and place an X.

When processing is accomplished, a **FAST-PATH** window will be displayed with the message transaction processed as shown in FIL015, (Pg. 15).

PARTIAL BACK ORDER CANCELED - SHIP-QTY CHANGED TO:

If partial backorder canceled is selected, the user must enter the SHIP-QTY changed to in the space provided at the end of the action. The quantity entered will replace the quantity on the Due Out File.

An error message will appear in the upper left corner of the screen if processing cannot be accomplished.

When processing is accomplished, a fast-path window will be displayed with the message transaction processed as shown in FIL015, (Pg. 15).

BACK ORDER CANCELED - REQUISITION SUBMITTED FOR DIRECT SHIP:

If BACK ORDER CANCELED - REQUISITION SUBMITTED FOR DIRECT SHIP is selected, an error message will appear in the upper left corner of the screen if processing cannot be accomplished.

When processing is accomplished, a FAST - PATH window will be displayed with the message, **TRANSACTION PROCESSED**. This Transaction has now been placed in the Automated Procurement function for further processing.

To complete the processing, input OPTION <13> at the enter OPTION field in the FAST - PATH window to access the Automated Procurement function. Refer to the AUTOMATED PROCUREMENT USER GUIDE for further processing.

BACK ORDER CANCELED - REQUISITION SUBMITTED TO GSA/DOD FOR DIRECT SHIP:

If BACK ORDER CANCELED - REQUISITION SUBMITTED TO GSA/DOD FOR DIRECT SHIP is selected, an error message will appear in the upper left corner of the screen if processing cannot be accomplished.

When processing is accomplished, a FAST - PATH window will be displayed with the message **TRANSACTION PROCESSED**. This Transaction has now been placed on QUEUE Management for further processing.

To complete the processing, input OPTION <12> at the enter OPTION field in the FAST - PATH window to access Queue Management. Refer to the **QUEUE**MANAGEMENT USER GUIDE for further processing.

BACK ORDER CANCELED - SUBSTITUTED NSN

If BACK ORDER CANCELED - SUBSTITUTE NSN is selected, the user must enter the substitute NSN in the space provided at the end of the action.

An error message will appear in the upper left corner of the screen if processing cannot be accomplished. When processing is accomplished, a FAST - PATH window will be displayed with the message, **TRANSACTION PROCESSED**. This Transaction has now been placed on Queue Management for further processing.

To complete the processing, input OPTION <12> in the enter OPTION field in the FAST - PATH window to access Queue Management. Refer to the **LIS QUEUE MANAGEMENT USER GUIDE** for further processing.

NOTE: If the user chooses to disregard the data and exit this screen before processing the transaction, the following OPTIONs are available. Input OPTION NUMBER and press **[ENTER]**.

OPTION <1> Select FAST - PATH EXIT to proceed to another transaction.

OPTION <9> Exit to FILE MAINTENANCE MAIN MENU - FIL010, (Pg. 13).

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

3.2 TRANSACTION PROCESSED - WINDOW

| 10/03/90 | LIS / FILE MAINTENANCE ** 04B CANCEL DUE OUT ** | FIL015 |
|----------------------------|---|------------|
| NSN: 2840 00 307 8960 | ISSUE VOUCHER: 92441230 | PRI :5 |
| TRANS-CD/TC-MOD : 80 B | D/O QUANTITY : 2 | |
| SELECT ONE ACTION FROM LIS | ST BELOW: | |
| ******* | ********* | ***** |
| ** TRANSACTION PROCESSE | | ** |
| ** | | ** |
| ** TRACKING-NBR: 902767 | 7042 NEXT TC/MOD: | ** |
| ** VOUCHER-NBR : 0276LG | GBD | ** |
| ** | VOUCHER: | * * |
| ** | CONTROL-NBR: | ** |
| ** | | ** |
| ** ENTER1234 | 1567891011 | 1213** |
| ** LIS IN | 1V | * * |
| ** HELP MAIN QUIT MA | AIN ISS REC ADJ FIL D/I CAT INQ | QUE PRC ** |
| ** | | * * |
| ********* | ************ | ****** |

FIGURE 7

After all fields are valid for input and the user has entered the data, the FAST - PATH window shown in Figure 7 is displayed with the message, **TRANSACTION PROCESSED**, in the REASON CODE TEXT field located in the window at the upper left corner.

NOTE: The TRANSACTION TRACKING NUMBER and the FILE Maintenance VOUCHER NUMBER have been mechanically assigned and are displayed in the FAST - PATH window. Specific information about TRANSACTION TRACKING NUMBERs and VOUCHER NUMBERs is contained in the LIS / VOUCHER CONTROL AND TRACKING NUMBER ASSIGNMENT USER GUIDE.

The FAST - PATH window can be used to access the other File Maintenance screens by inputting the appropriate TRANSACTION CODE and MODIFIER, NSN and VOUCHER NUMBER or CONTROL NUMBER, or OPTION NUMBER. See **FAST - PATH FEATURE** - FIL015, (Pg. 15).

3.3 THE FAST - PATH FEATURE

| 10/03/90 | LIS / FILE MAINTENANCE ** 04B CANCEL DUE OUT ** | FIL015 |
|----------------------------|---|---------------|
| NSN : 5820 01 233 0379 | ISSUE VOUCHER: 924412 | 3 PRI :5 |
| TRANS-CD/TC-MOD: 80B | D/O QUANTITY : 1 | |
| SELECT ONE ACTION FROM LIS | ST BELOW: | |
| ******* | ********** | ***** |
| ** TRANSACTION PROCESSE | | * * |
| ** | | * * |
| ** TRACKING-NBR: 900012 | 2560 NEXT TC/MOD: | * * |
| ** VOUCHER-NBR : 9001AC | CBD NSN: | ** |
| ** | VOUCHER: | ** |
| ** | CONTROL-NBR: | ** |
| ** | | * * |
| ** ENTER1234 | 456789101 | 11213** |
| ** LIS IN | NV. | * * |
| ** HELP MAIN QUIT MA | AIN ISS REC ADJ FIL D/I CAT I | NQ QUE PRC ** |
| ** | | ** |
| ************* | * | ***** |

FIGURE 8

The FAST - PATH feature, within the Inventory Management Subsystem, is designed to give direct access to other processing screens or functions without having to exit to a selection menu. After entering a transaction, a window as shown above is displayed. The message, **TRANSACTION PROCESSED**, is displayed in the REASON CODE TEXT.

To use the FAST - PATH, the next TC/MOD is required. NSN and VOUCHER or CONTROL-NBR, are required for some TRANSACTION CODES.

OR

The user can choose to input an OPTION NUMBER at the enter field to access a specific function menu, as allowed by assigned security level. For example, to access the Adjustment Menu, input <7> in the enter field and press [ENTER].

3.4 06Y RELEASE DUE OUT

| 10/03/90 | LIS / FILE MAINTENANCE 06Y RELEASE BACKGROUND ** | FIL020 | |
|--|--|------------|--|
| NSN : 2840 00 307 8960 | ISSUE VOUCHER | : 01613401 | |
| D/O QUANTITY : 4 | ORIG TC/MOD | : 67B_ | |
| RELEASE QUANTITY : | PRI | : 5_ | |
| PRESS ENTER TO PROCESS OR 1 - SELECT FAST PATH EXITS 9 - EXIT TO FIELD/FILE MAINTENANCE MENU ENTER OPTION: 99 - EXIT TO INVENTORY MANAGEMENT MAIN MENU | | | |

FIGURE 9

OPTION <2> of the **LIS FILE MAINTENANCE MAIN MENU - FIL**010, (Pg. 13) is to manually release a Backorder for shipment from the Due Out File, TRANSACTION CODE 06Y. Access is by security level 3, 4 or 5.

The RELEASE QUANTITY is the only data element that can be changed. Input the RELEASE QUANTITY and press **[ENTER]**.

NOTE: If the user chooses to disregard the data and exit this screen before processing the transaction, the following options are available. Input OPTION NUMBER and press **[ENTER]**.

OPTION <1> Select FAST - PATH EXIT to proceed to another transaction.

OPTION <9> Exit to **FILE MAINTENANCE MAIN MENU** - **FILO10**, (Pg. 13).

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

An error message will appear in the upper left corner of the screen if processing cannot be accomplished. When processing is accomplished, a FAST - PATH window will be displayed with the message, **TRANSACTION PROCESSED**. Refer to FIL015, (Pg. 15).

3.5 03B MODIFY DUE OUT

| 10/03/90 LI | S / FILE MA 03B MODIFY | _ | FIL025 |
|--|---------------------------|---------------------------------------|------------|
| NSN : 2840 00 307 8960 _ | | VOUCHER | : 92441234 |
| TRANSACTION CODE/MODIFIER: | 80 B | PRI | : 4_ |
| ESTIMATED RELEASE DATE : | 012991 | DATE REQUIRED | : 102090 |
| TYPE BACK ORDER CODE : | 1 | CONDITION CODE | : S_ |
| SUPPLY SUPPORT CODE : | E69110475 | COST CENTER CODE | : |
| ADVICE CODE : | _ | | |
| PRESS ENTER TO PROCESS OR 1 - SELECT FAST PATH EXITS | | | |
| ENTER OPTION: | | FO FIELD/FILE MAIN FO INVENTORY MANAG | |

FIGURE 10

OPTION <3> of the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13) is to modify the Due Out File, TRANSACTION CODE 03B. Access is by security level 3, 4 or 5.

The NSN, VOUCHER NUMBER, TRANSACTION CODE and MODIFIER, PRI, ESTIMATED RELEASE DATE, DATE REQUIRED (applicable to a PRI 4) TYPE BACK ORDER CODE, CONDITION CODE, SUPPLY SUPPORT CODE (SSC),

COST CENTER CODE (applicable to Region A and F) and ADVICE CODE displayed with data from the Due Out File.

The NSN, VOUCHER NUMBER and TRANSACTION CODE MODIFIER are constant and cannot be changed. All other data elements can be modified.

NOTE: If the user chooses to disregard the data and exits this screen before processing the transaction, the following OPTIONs are available. Input OPTION NUMBER and press **[ENTER]**.

OPTION <1> Select FAST - PATH EXIT to proceed to another transaction.

OPTION <9> Exit to FILE MAINTENANCE MAIN MENU - FIL010, (Pg. 13).

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

3.6 01T DELETE MASTER INVENTORY

| 10/03/90 LIS / FILE MAIN ** 01T DELETE INVENT | | FIL030 |
|---|--|------------------|
| NSN : 2840 00 307 8960 _ DESCRIPTION : APP-TO-CD : STD-UNIT-PRICE: UNIT OF ISSUE : CATG/ACCT : | TOTAL ONHAND SERVICEABLE REPARABLE DUE-IN FACILITY IN-SHOPS SURVEY | : : : : |
| ITEM MANAGER : PRE-INVENTORY : CURR-STATUS-CD: | BORROWED LOANED DUE-IN-ACQ DUE-OUT BUDGET-YEAR | : : : : |
| DO YOU WANT TO DELETE RECORD (Y/N) : | FIVE-YEAR COMMITTED | : : |
| DO YOU WANT TO PLACE ON QUEUE (Y/N) : _ | DIR-SHIP-SCH APPROVED | : : |
| PRESS ENTER TO PROCESS OR 1 - SELECT OR 9 - EXIT TO ENTER OPTION: 99 - EXIT TO | O FIELD/FILE MAINTE | |

FIGURE 11

OPTION <4> of the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13) is to delete a Master Inventory Record, Transaction Code 01T. Access is by security level 3, 4 or 5.

The data displayed is the actual view of the Inventory Master Record. The following criteria must be meet to effect a delete action.

A CURRENT STATUS CODE <3> or <4> cannot be present on the record.

The user must input a response to the prompt

DO YOU WANT TO DELETE RECORD (Y / N): ____

If the record cannot be deleted due to one of the conditions described above, an error message will appear in the upper left corner of the screen,

TOTAL ONHAND QUANTITY MUST = ZERO, PRESS ENTER TO BUILD QUEUE EXCEPTION.

If the user, chooses to build the Queue Exception, press **[ENTER]**. The FAST - PATH window shown in FIL030, (Pg. 28), will display the message,

ACTION NOT ACCOMPLISHED-SOME OR ALL OF THE MASTER QTYS ARE NOT ZERO

or a similar message.

NOTE: If the User chooses not to build the Exception on the Queue, input OPTION Number and press **[ENTER]**.

OPTION <1> Select FAST - PATH EXIT to proceed to another transaction.

OPTION <2> Exit to FILE MAINTENANCE MAIN MENU - FIL010, (Pg. 13).

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

3.7 TRANSACTION UNPROCESSED - WINDOW

| TOTAL ONHAND QUANTITY MUST = ZERO, PRESS ENTER T | O BLD QUEUE | |
|--|--------------------|---------------------|
| 10/03/90 LIS / FILE MAINTENAN ** 01T DELETE INVENTORY R | | FIL030 |
| NSN : 2840 01 307 8960 TOTAL | ONHAND | : 6 |
| DESCRIPTION : SUP ASSY 6738368 | SERVICEABLE | : 3 |
| APP-TO-CD : ASR | REPARABLE | : 3 |
| STD-UNIT-PRICE : 148.00 | DUE IN FACILITY | : 3 |
| ************* | ****** | ***** |
| ** ACTION NOT ACCOMPLISHED - SOME OR ALL OTH TH | IE MASTER QTYS ARE | NOT ZERO** |
| ** TRACKING-NBR: 901991383 NEXT TC/MOD: | | ** |
| ** VOUCHER-NBR : 0199LGBD NSN: | | ** |
| ** VOUCHER: | | * * |
| ** CONTROL-NBR: | | ** |
| ** | | * * |
| ** ENTER123456789 | 9101112 | 13 ** |
| ** LIS INV | | ** |
| ** HELP MAIN QUIT MAIN ISS REC ADJ FIL | D/I CAT INQ Q | UE PRC ** |
| ** | | * * |
| ************** | ****** | * * * * * * * * * * |

FIGURE 12

In some instances when a transaction is unable to process, or the transaction is passed to Queue Management, a REASON CODE TEXT will be displayed on the FAST - PATH window in the upper left corner.

The REASON CODE TEXT can be one of several messages including:

ACTION NOT ACCOMPLISHED - SOME OR ALL THE MASTER QTYS ARE NOT ZERO.

INV RECD HAS CSC 4 AND TRANS WILL NOT PROCESS. ITEM IN PHY INV.

An Exception Notice is placed on the Item Manager's Queue Management for review / action. The user can continue processing.

NOTE: The TRANSACTION TRACKING NUMBER and the File Maintenance VOUCHER NUMBER have been assigned and are displayed in the FAST - PATH window. Specific information about TRANSACTION TRACKING NUMBERS and VOUCHER NUMBERs is contained in the

LIS VOUCHER / CONTROL AND TRACKING NUMBER ASSIGNMENT USER GUIDE.

The FAST - PATH window can be used to access other File Maintenance screens by inputting the appropriate TRANSACTION CODE and MODIFIER, NSN and VOUCHER NUMBER or CONTROL NUMBER, or OPTION NUMBER. See **FAST - PATH FEATURE** - FIL015, (Pg. 21).

3.8 03T MODIFY MASTER INVENTORY

| 10/03/90 LIS / FILE MAINTENANCE ** 03T MODIFY MASTER INVENTORY ** | | | | | |
|--|-----|--------------------------------|-------------|--|--|
| NSN | : | DESCRIPTION : | _ | | |
| MGMT-CD | : _ | SAFETY-STOCK: RESERVED-QTY : | | | |
| IM | : | SS-FRZ-IND : _ APPROVED-QTY : | | | |
| PSC | : | QUP-TYPE : MAX-ISSUE-QTY: | | | |
| PLT | : | QUP-CD : _ ACQ-REV-PT : | | | |
| PLT-FRZ-IND | : _ | RGN-ACTION : _ ACQ-FRZ-INC : _ | | | |
| RSC | : | S-AND-I : _ SCHED-REPAIR : | | | |
| RLT | : | SHELF-LIFE : SCHED-FRZ-IND: _ | | | |
| PLT-FRZ-IND | : _ | REP-RAT-CD : _ FORCASTED-DMD: | | | |
| TYPE-PRICE | : _ | REP-RAT-DATE: _ DIR-SHIP-SCHD: | | | |
| SPEC-HAND-CD | : _ | SER-NBR-CNTL: _ REP-REVEIW-PT: | | | |
| ESSENTIAL-CD | : _ | LAT-PROC-PRC: REP-FRZ-IND : | | | |
| SMR-CD | : | EST-REP-COST: | | | |
| PRESS ENTER TO PROCESS 1 - SELECT FAST PATH EXITS OR 9 - EXIT TO FIELD/FILE MAINTENANCE MENU ENTER OPTION: 99 - EXIT TO INVENTORY MANAGEMENT MAIN MENU | | | | | |

FIGURE 13

OPTION <5> of the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13) is to modify the Master Inventory Record, TRANSACTION CODE 03T. The NSN, DESCRIPTION, UNIT OF ISSUE and CATEGORY ACCOUNT CODE (C / A) are constant and cannot be changed.

All other fields can be modified, subject to security level.

The screen shown in FIL035, (Pg. 30) is tailored for security level 2, 3, 4 or 5 (Inventory Management personnel and Supervisors).

NOTE: When 03T MODIFY MASTER INVENTORY - FIL035, (Pg. 30) is accessed by other security levels, the fields displayed are limited to those for which update is authorized for their respective security level. These fields are identified in paragraph 1.3 SECURITY LEVELS FOR FILE MAINTENANCE, (Pg. 3). Conversely, Inventory Management personnel cannot update fields excluded from their security level.

NOTE: If the user chooses to disregard the data and exit the screen before processing the transaction, the following options are available. Input OPTION NUMBER and press **[ENTER]**.

OPTION <1> Select FAST PATH EXIT to proceed to another transaction.

OPTION <2> Exit to FILE MAINTENANCE MAIN MENU - FIL010, (Pg. 13).

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

An error message will appear in the upper left corner of the screen if processing cannot be accomplished. When processing is accomplished a FAST - PATH window will be displayed with the message, **TRANSACTION PROCESSED**. See FIL015, (Pg. 21).

3.9 03L MODIFY MANAGEMENT FIELDS

| 10/03/90 | LIS / FILE N ** 03L MODIFY MANAG | | FIL040 | | | |
|---|----------------------------------|--|--------|--|--|--|
| NSN :2840 00 307 | 8960 _ DESCRIPTION | : SUP ASSY 6738368 C/A : | F6 | | | |
| APP-TO-CD : | ISS-TRAN-FYTD | : CURR-ISS-TRANS : | | | | |
| DISPOSAL-CD : | _ ACQ-REV-BRKS | : CURR-REC-TRANS : | | | | |
| REP-SPEC-CD : | SURVEY-FYTD | : LAST-DISP-REV : | | | | |
| CONTRACT-NBR : | ROT-DMD-12-MO | : REPAIR-LEVEL : | | | | |
| EOQ-CD : | _ CMD-NORMAL | : RL-FRZ-IND : | _ | | | |
| OLD-AVG : | CMD-NON-NORMAL | : REIMB-LONG-ACQ : | | | | |
| ACQ-LEVEL : | CMD-ROTABLE | : NON-REIMB-LONG : | | | | |
| TREND-FACTOR : | CMD-OTHER | : NBR-MO-IN-SYS : | | | | |
| DATE-FIRST-REC : | LOW-RETENTION | : NBR-MO-IN-CAT : | | | | |
| QTY-RECD-FYTD : | LRL-FRZ-IND | : _ DATE-LAST-DMD : | | | | |
| REC-TRANS-FTYD : | UPP-RETENTION | : DATE-LAST-ACT : | | | | |
| DATE-LAST-REC : | URL-FRZ-IND | : _ ANN-REP-SCH-QTY: | | | | |
| PRESS ENTER TO P | 9 - EXIT TO | FAST PATH EXITS FIELD/FILE MAINTENANCE MED INVENTORY MANAGEMENT MAIN | _ | | | |
| ENTER OFITON: 95 - EATT TO INVENTOR! MANAGEMENT MAIN MENO | | | | | | |

FIGURE 14

OPTION <6> of the LIS FILE MAINTENANCE MAIN MENU - FIL010, (Pg. 13) is to modify the Management Master Inventory Record, TRANSACTION CODE 03L. Access is by security level 2, 3, 4, or 5. The NSN, DESCRIPTION and CATEGORY ACCOUNT CODE (C/A) are constant and cannot be changed. All other elements can be modified.

OPTION <1> Select FAST PATH EXIT to proceed to another transaction.

OPTION <2> Exit to **FILE MAINTENANCE MAIN MENU** - **FILO10**, (Pg. 13).

OPTION <99> Exit to **INVENTORY MGT. MAIN MENU** - **INV001**, (Pg. 10).

3.10 03T/03Q MODIFY WAREHOUSE LOCATIONS

| | S / FILE MAINTENANCE MODIFY WAREHOUSE LOCATIONS ** | FIL045 |
|---------------------------|--|-----------|
| NSN : | _ DESCRIPTION : | |
| PRIME LOCATION : | | |
| SECONDARY-LOCATION | : | _ |
| | | _ |
| | | |
| PRESS ENTER TO PROCESS OR | <pre>1 - SELECT FAST PATH EXITS 9 - EXIT TO FIELD/FILE MAINTENANCE</pre> | E MENU |
| ENTER OPTION: | 99 - EXIT TO INVENTORY MANAGEMENT | MAIN MENU |

FIGURE 15

OPTION <7> of the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13) is to modify the PRIME and SECONDARY WAREHOUSE LOCATIONs on the Master Inventory Record. Access is by security level 6, C or K.

The NSN and DESCRIPTION are constant and cannot be changed.

This screen can be used to establish, change or delete the PRIME and SECONDARY WAREHOUSE LOCATIONS separately or concurrently.

OPTION <1> Select FAST PATH EXIT to proceed to another transaction.

OPTION <2> Exit to **FILE MAINTENANCE MAIN MENU** - **FIL010**, (Pg. 13).

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

3.11 03A MODIFY ADVANCE DUE-IN

| 10/03/90 LIS / FILE MAINTE ** 03A MODIFY ADVANCE | |
|--|--|
| NSN : 2840 01 050 1623 _ | CONTROL-NBR : 12350 |
| DUE-IN-DATE : 101391_ | PRI-CD : 5_ |
| CONTRACT-NBR : | TRANS-CD/MOD : 40 A |
| QUANTITY : 12 | COND-CD : S_ |
| PRESS ENTER TO PROCESS OR 1 - SELECT FAST 9 - EXIT TO FIEL | PATH EXITS LD/FILE MAINTENANCE MENU |
| ENTER OPTION: 99 - EXIT TO INVI | ENTORY MANAGEMENT MAIN MENU |

FIGURE 16

The eighth option of the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13) is to modify the Advance Due In Record, TRANSACTION CODE 03A. Access is by security level 2, 3, 4 or 5.

The NSN, CONTROL NBR, DUE-IN-DATE, PRI-CD, CONTRACT-NBR, TRANS-CD/MOD, QUANTITY, AND COND-CD are automatically displayed from the Advance Due In record.

The NSN, CONTROL-NBR and TRANSACTION CODE MODIFIER are constant and cannot be changed. All other data elements can be modified.

OPTION <1> Select FAST PATH EXIT to proceed to another transaction.

OPTION <2> Exit to **FILE MAINTENANCE MAIN MENU** - **FILO10**, (Pg. 13).

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

3.12 03D MODIFY DUE-IN

| 10/03/90 | LIS / FILE MAI: ** 03D MODIFY I | _ | FIL055 |
|----------------|---|---------------------------------|------------------|
| NSN : 5820 (| 01 211 5302 _ | CONTROL-NBR | : 1535123456_ |
| DUE-IN-DATE | : 101491 | PRI-CD | : 5_ |
| CONTRACT-NBR | : 2 | TRANS-CD/MOD | : 40 D |
| QUANTITY | : | COND-CD | : S_ |
| SSC | : 769420101 | | |
| PRESS ENTER TO | PROCESS OR 1 - SELECT FA 9 - EXIT TO F | ST PATH EXITS IELD/FILE MAIN | VTENANCE MENU |
| ENTER OPTION | : 99 - EXIT TO I | NVENTORY MANAC | GEMENT MAIN MENU |

FIGURE 17

OPTION <9> of the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13) is to modify the Due In Record, TRANSACTION CODE 03D. Access is by security level 2, 3, 4, or 5.

The NSN, CONTROL NBR, DUE-IN-DATE, PRI-CD, CONTRACT-NBR, TRANS-CD/MOD, QUANTITY, COND-CD and SSC are automatically displayed from the Due In File.

The NSN, CONTROL-NBR and TRANSACTION CODE MODIFIER are constant and cannot be changed. All other data elements can be modified.

OPTION <1> Select FAST PATH EXIT to proceed to another transaction.

OPTION <2> Exit to **FILE MAINTENANCE MAIN MENU** - **FIL010**, (Pg. 13).

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

3.13 03F MODIFY DUE IN FACILITY

| | IS / FILE MA: MODIFY DUE | INTENANCE IN FACILITY | * * | FIL060 |
|---------------------------|-----------------------------|--------------------------|--------------|---------|
| NSN : 5985 01 309 9159 | _ | CONTROL-NBR | : | |
| DUE-IN-DATE : 121490 | | COST CD | : | |
| FOLLOW-UP-DATE : 031491 | | AGREEMENT-NBF | : | |
| SSC : C69522 | 013 | COST-CNTR | : | |
| JOB-ORDER-NBR : | | | | |
| PRESS ENTER TO PROCESS OR | | FAST PATH EXI | | MENU |
| ENTER OPTION: | 99 - EXIT TO | O INVENTORY MA | ANAGEMENT MA | IN MENU |

FIGURE 18

OPTION <10> of the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13) is to modify the Due In Facility Record, TRANSACTION CODE 03F. Access is by security level 2, 3, 4, or 5.

The NSN, CONTROL NBR, DUE-IN-DATE, COST CD, FOLLOW-UP-DATE, AGREEMENT-NBR, SSC, COST-CENTER and JOB-ORDER-NBR are automatically displayed from the Due In Facility File.

The NSN, CONTROL-NBR and TRANSACTION CODE MODIFIER are constant and cannot be changed. All other data elements can be modified.

OPTION <1> Select FAST PATH EXIT to proceed to another transaction.

OPTION <2> Exit to **FILE MAINTENANCE MAIN MENU** - **FIL010**, (Pg. 13).

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

3.14 03N MODIFY DUE-IN SHOPS

| 10/03/90 | LIS / FILE MAINTENANCE 03N MODIFY DUE IN SHOPS ** | FIL065 |
|---------------------------|--|--------------|
| NSN : 7035 01 084 9716 | _ CONTROL-NBR : 01 | 993100 |
| DUE-IN-DATE : 01159 | 1 | |
| WORK-ORDER-NBR : | | |
| SSC : A6973 | 88 | |
| PRESS ENTER TO PROCESS OR | 1 - SELECT FAST PATH EXITS 9 - EXIT TO FIELD/FILE MAINTEN | ANCE MENU |
| ENTER OPTION: | 99 - EXIT TO INVENTORY MANAGEMEN | NT MAIN MENU |

FIGURE 19

OPTION <11> of the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13) is to modify the Due In Shops Records, TRANSACTION CODE 03N. Access is by security level 2, 3, 4, or 5.

The NSN, CONTROL-NBR, DUE-IN-DATE, WORK-ORDER-NBR, and SSC are automatically displayed from the Due In Shops File.

The NSN and CONTROL-NBR are constant and cannot be modified. All other data elements can be modified.

OPTION <1> Select FAST PATH EXIT to proceed to another transaction.

OPTION <2> Exit to **FILE MAINTENANCE MAIN MENU** - **FILO10**, (Pg. 13).

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

3.15 03P MODIFY BORROWED

| 10/03/90 LIS / FILE M ** 03F MODIFY | | FIL070 |
|--|---|---------|
| NSN : 5985 01 304 8407 _ | CONTROL-NBR : 2001 | |
| ROUTE-SYMBOL : 480 | COND-CD : S_ | |
| DUE-OUT-DATE : 112090 | AGREEMENT-NBR : | _ |
| SSC : 269710366 | SERIAL-NBR : A123 | |
| | FAST PATH EXITS FIELD/FILE MAINTENANCE ME INVENTORY MANAGEMENT MAIN | |
| HIVIER OF THORY — | TIVELUCICI PREMODIFICIUL PARIN | 1.11110 |

FIGURE 20

OPTION <12> of the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13) is to modify the Borrowed Record, TRANSACTION CODE 03P. Access is by security level 2, 3, 4, or 5.

The NSN, CONTROL-NBR, ROUTING-SYMBOL, COND-CD, EST-RELEASE-DATE, AGREEMENT-NBR, SSC AND SERIAL-NBR are automatically displayed from the Borrowed File.

NOTE: If the user chooses to disregard the data and exit this screen before processing the transaction, the following options are available. Input OPTION NUMBER and press **[ENTER]**.

OPTION <1> Select FAST PATH EXIT to proceed to another transaction.

OPTION <2> Exit to **FILE MAINTENANCE MAIN MENU** - **FIL010**, (Pg. 13).

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

3.16 03M MODIFY LOANED

| 10/03/90 LIS / FILE MAINTENANCE FIL075 ** 03M MODIFY LOANED ** | | | | |
|--|---|--|--|--|
| NSN : 5825 01 164 5694 _ | CONTROL-NBR : 2006 | | | |
| ROUTE-SYMBOL : 480 | COND-CD : S_ | | | |
| DUE-OUT-DATE : 112591 | AGREEMENT-NBR: EMER | | | |
| SSC : 269714201_ | SERIAL-NBR : 49226 | | | |
| PRESS ENTER TO PROCESS OR 1 - SEL | | | | |
| | T TO FIELD/FILE MAINTENANCE MENU T TO INVENTORY MANAGEMENT MAIN MENU | | | |

FIGURE 21

OPTION <13> of the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13) is to modify the loaned Record, TRANSACTION CODE 03M. Access is by security level 2, 3, 4, or 5.

The NSN, CONTROL-NBR, ROUTING-SYMBOL, COND-CD, DUE-IN-DATE, AGREEMENT-NBR, SSC, and SERIAL-NBR are automatically displayed from the Loaned File.

NOTE: If the user chooses to disregard the data and exit this screen before processing the transaction, the following options are available. Input OPTION NUMBER and press **[ENTER]**.

OPTION <1> Select FAST PATH EXIT to proceed to another transaction.

OPTION <2> Exit to **FILE MAINTENANCE MAIN MENU** - **FIL010**, (Pg. 13).

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

3.17 03J MODIFY DEMAND MASTER

| 12/02/91 | LIS / FILE MAINTENANCE ** 03J MODIFY DEMAND MASTER ** | FIL080 |
|---------------------|---|-----------------|
| NSN : 5825 01 142 | 8131 _ | |
| THE FOLLOWING FIELD | S ARE FOR THE SPECIFIED MONTH AND | YEAR |
| MONTH : YEAR | : ACTION | |
| NORMAL-DMD : | ACTION TYPES: | 2 - ADD |
| NONORMAL-DMD : | | 3 - SUBTRACT |
| ROTABLE-DMD : | | 4 - ESTABLISH |
| OTHER-DMD : | <u> </u> | |
| NBR-RECEIPT-TRANS : | <u>—</u> | |
| NBR-ISSUE-TRANS : | <u>—</u> | |
| PRESS ENTER TO PROC | ESS 1 - SELECT FAST PATH EXIT | |
| OR | 9 - EXIT TO FIELD/FILE MAINT | TENANCE MENU |
| ENTER OPTION: | 99 - EXIT TO INVENTORY MANAGE | EMENT MAIN MENU |

FIGURE 22

OPTION <14> of the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13) is to modify the demand history data on the Master Inventory File, TRANSACTION CODE 03J. Access is by security level 2, 3, 4, or 5. The NSN is displayed from the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13). The section of the screen below the statement, THE FOLLOWING FIELDS ARE FOR THE SPECIFIED MONTH AND YEAR, is to input the MONTH and YEAR that is to be updated.

The data below these fields can be modified with:

- 2 ADD a quantity to the Demand Master
- 3 SUBTRACT a quantity from the Demand Master
- 4 ESTABLISH the quantity in the Demand Master

NOTE: If the user chooses to disregard the data and exit this screen before processing the transaction, the following options are available. Input OPTION NUMBER and press **[ENTER]**.

OPTION <1> Select FAST PATH EXIT to proceed to another transaction.

OPTION <2> Exit to **FILE MAINTENANCE MAIN MENU** - **FIL010**, (Pg. 13).

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

An error message will appear in the upper left corner of the screen if processing cannot be accomplished. When processing is accomplished a FAST - PATH window will be displayed with the message, **TRANSACTION PROCESSED**. See FIL015, (Pg. 21).

NOTE: Due to system revisions in November 1991, this request will now process online, rather than in batch mode at the end of the month's cycle. The effects of the changes can be seen by accessing the Demand History Inquiry from the Inquiry Main Menu

3.18 09R REQUEST STATUS CARD

| 10/03/90 | LIS / FILE MAINTENANCE 09R REQUEST STATUS CARD ** | FIL085 |
|---|--|--------|
| | NSN : | |
| | : | |
| | : | |
| | : | |
| PRESS ENTER TO PROCESS OR ENTER OPTION: | 1 - SELECT FAST PATH EXIT 9 - EXIT TO FIELD/FILE MAIN 99 - EXIT TO INVENTORY MANAG | |

FIGURE 23

OPTION <15> of the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13) is to request a STATUS CARD, TRANSACTION CODE 09R. Access is by security level 2, 3, 4 or 5.

The NSN will be displayed if entered on the **LIS FILE MAINTENANCE MAIN MENU** - FIL010, (Pg. 13). If OPTION <15> is selected and the NSN is not entered the screen will be blank. Input from 1 to 10 NSNs per request, to print a STATUS CARD for a specific NSN.

OPTION <1> Select FAST PATH EXIT to proceed to another transaction.

OPTION <2> Exit to **FILE MAINTENANCE MAIN MENU** - **FIL010**, (Pg. 13).

OPTION <99> Exit to **INVENTORY MGT. MAIN MENU** - **INV001**, (Pg. 10).

An error message will appear in the upper left corner of the screen if processing cannot be accomplished. When processing is accomplished a FAST - PATH window will be displayed with the message, TRANSACTION PROCESSED. See FIL015, (Pg. 21).

NOTE: This request is not processed online. It will be processed in batch mode at the end of the day's cycle.

4.0 SPECIAL FEATURES AND APPLICATIONS

File Maintenance contains some special features to enhance the capabilities of the function.

4.1 ERROR MESSAGE - EXAMPLE

| NO RECORD FOUND FOR THIS NSN | | | |
|--------------------------------|--------------|-----------------------------|----------|
| 11/03/90 Li | S/FILE MAINT | ENANCE F | 'IL010 |
| | ** FILE MENU | U ** | |
| | | | |
| 1 - CANCEL DUE OUT | (04B) | 11 - MODIFY IN SHOPS | (03N) |
| 2 - RELEASE DUE OU | (06Y) | 12 - MODIFY BORROWED | (03P) |
| 3 - MODIFY DUE OUT | (03B) | 13 - MODIFY LOANED | (03M) |
| 4 - DELETE MASTER INVENTORY | (01T) | 14 - MODIFY INVENTORY DEMA | ND (03J) |
| 5 - MODIFY MASTER INVENTORY | (03T) | 15 - REQUEST DEMAND INQUIR | Y (09D) |
| 6 - MODIFY MANAGEMENT FIELDS | (03L) | 16 - REQUEST STATUS CARD | (09R) |
| 7 - MODIFY SECONDARY LOCATIONS | (03T/03Q) | 17 - MASS ITEM MANAGER CHA | NGE |
| 8 - MODIFY ADVANCE DUE IN | (03A) | | |
| 9 - MODIFY DUE IN | (03D) 9 | 99 - EXIT TO INVENTORY MAN. | AGEMENT |
| 10 - MODIFY DUE IN FACILITY | (03F) | MAIN MENU | |
| | ENTER OPTION | т• Б | |
| | ENIER OFIION | · 5_ | |
| OPTION 1-14 | NSN: | *1560 00 858 2244 _ | |
| 1-3 | VOUCHER-NBR: | | |
| 8-13 | CONTROL-NBR: | | |
| | | | |

FIGURE 25

An error message will appear in the upper left corner of the screen when invalid / incomplete data is input. The error message will display information for course of action.

The cursor will be positioned at the first invalid field on the screen. In Figure 25 the cursor is located at the point of the asterisk (*) for a verification of the NSN. Edit the information for validity and press[ENTER].

If additional fields are invalid, the messages will continue and the cursor will relocate until all fields are valid.

The user can choose to disregard the data and exit the screen before processing the transaction. Input one of the following OPTIONS:

OPTION <99> Exit to INVENTORY MGT. MAIN MENU - INV001, (Pg. 10).

4.2 FIELD DEFINITIONS - EXAMPLE

```
10/03/90
                                                          FIL010
                            FILE MAINTENANCE
                             MATN MENU
     * * *
 * * *
                                                           * * *
 * * *
                                                           * * *
     NSN
                                                           * * *
     NATIONAL STOCK NUMBER ASSIGNED FOR CONTROL PURPOSES TO
 * * *
     IDENTIFY ITEMS OF SUPPLY.
                               CONSISTS OF 4 - DIGIT FEDERAL
     SUPPLY CLASSIFICATION (FSC), 2 - DIGIT NATO COUNTRY CODE
     AND A 7 - DIGIT NONSIGNIFICANT SERIAL NUMBER.
                                                           * * *
 * * *
                                                           * * *
 * * *
                                                           * * *
```

FIGURE 26

FIELD DEFINITION is a feature of this function. It allows the user to obtain the definition for a specific data field. It is available on all data entry fields. If a data field is required and the user is not sure what data to input, this feature is beneficial.

When a definition is desired, enter a question mark (?) in the first position of the data field. Press **[ENTER]**. A window will be displayed on the screen with a definition of the data field selected.

After viewing the information, press **[ENTER]** and the original screen will return and processing.



This User Guide has been prepared by the

Federal Aviation Administration Logistics Center Automation Division, AML-100 Mike Monroney Aeronautical Center 6500 S. MacArthur Boulevard Oklahoma City, OK 73169 (405) 954-3447